SET UP DATA SOURCE USING MELSEC PROTOCOL

In this Appendix...

Set up data source for a device using MELSEC protocol	К-З
PLC settings	К-4
Select a communication protocol	К-9
Add variables (new, import)	K-11
Manually add new variables	K-11
Import variables from a file (or device)	K-12
Test variables	K-13
Connecting StrideLinx to Q series Ethernet module QJ71E71-100 with N	/IELSEC
Protocol	K-14

APPENDIX

This manual covers the StrideLinx platform available from 2017 through 2021.

For details covering the StrideLinx Cloud 2.0 platform available after April 2021, please <u>click here</u> to link to that manual.

The StrideLinx Cloud 2.0 manual includes details describing the <u>Activation Code</u> model of Data Logging, Cloud Notify and other add-on features.

For information on the migration wizard from the original platform to StrideLinx Cloud 2.0, <u>click here</u>.

Set up data source for a device using MELSEC protocol

Supported hardware and firmware

StrideLinx routers support Cloud Logging via MELSEC Communication in firmware 3.17 and newer, for the following Mitsubishi PLCs:

- MELSEC-L Series: LO2CPU-P*
- MELSEC-Q Series
- MELSEC iQ-R Series: R08CPU*
- MELSEC iQ-F Series

* Other CPUs in this series may also be supported, but are unconfirmed.



NOTE: Please first activate Cloud Logging or start the 30 day free trial if you haven't already.

The first step in Cloud Logging is setting up a data source. This is done by selecting a communication protocol and defining the variables. This appendix shows you how to do this for a Mitsubishi PLC in both MELSOFT GX Works2 and GX Works3.

PLC settings

Depending on the type of Mitsubishi PLC you're using, the setup of the PLC has to be performed in either GX Works2 or GX Works3:

- L and Q series are set up using GX Works2.
- iQ-F and iQ-R series are set up using GX Works3.

GX Works2

Setting up the CPU Module enables the PLC to communicate with an external device (i.e., your StrideLinx router). This can be done by following the next steps:

- In the Project Window, open **Parameter** > **PLC Parameter** and go to the tab **Built-in Ethernet Port Setting**.
- If you haven't already, enter an **IP address** for the CPU Module (1) and a **Subnet Mask Pattern** (usually 255.255.255.0).
- Check the option "Set Open Setting in Ethernet Configuration window" and press Ethernet Conf (2).



• On a new row, select protocol "TCP", select open system "MC Protocol" and choose a Host Station Port Number between 1025-4999 or 5010-65534.

B	uilt-in l	Ethernet P	ort Open Setting						×
ľ							IP Addres	s/Port No. Input Format	DEC •
Ľ		Protocol	Open System	TCP Connection	Host Station Port No.	Destination IP Address	Destination Port No.	Start Device to S Predefined Protocol Oper	Rore ration Status
	1	UDP +	MELSOFT Connection						
	2	TCP .	MC Protocol		1025				
	3						1		13
	4								
Ξ.	5			-			3		2
d.	6		•	•			-		12
1	7						-		
	8								12
	9						-		
	10			•					2
4	11			•					
	12							-	
	23						-		
	14	- 0					-	1	
	15							-	19
s	(") I Plea	P Address se enter ti	and Port No. will be displa te value according to the r	ived by the selects	ed format.	Cancel			



NOTE: TCP or UDP?

We support both the TCP and UDP protocols but recommend using TCP as this protocol is less error-prone.

Your PLC is now ready and you can continue setting up your StrideLinx router by selecting a communication protocol.

GX Works3

Setting up the CPU Module enables the PLC to communicate with an external device (i.e., your StrideLinx router). This can be done by following the next steps:

- In the Navigation pane, go to **Parameter** > **CPU** (FX5UCPU in the example below) > **Module parameter**.
- Open the **Ethernet Port** parameters.



- Expand Basic Settings in the Item List and double click External Device Configuration.
- Expand Setting Item **External Device Configuration** and open the External Device Configuration window by double clicking "<**Detailed Setting**>".

All Control and Co				1.1. • (Denved Selector)					
10 A 10	Strag Service		and any first of the		WALLS CON				
and the second second	Freid the Setting tiers to Search		And the later	549	an Aug (a) and a				
Person		1000	La Patron		121.2 X 141				
	70		IF-Iddaes		Ospier Target: /				
Label	U- Ca Base Setres		Subset Mark						
Device Common State	Over Node Settings COLLAR KE Basic Settings		Owlast Oakway	A1017					
Dates Memory	HODE/UL/TCP Settings		CC 4-4 HF Base Sellings	(ee)					
Davke initial Value	Exercit Device Configuration		To Los or Net to Use CC-Link ISF Basic Sering	Deze					
	a di signa ante		Network Configuration Settings	(Dealed Set up					
System President	41		Rafuelt Selings	- Celulat Set no-					
ALCONO CONTRACTOR			To have the to the structure former	Baller					
C. Module Parameter			Dana/sageset	Called Set of					
C Distance Post	Observer Prof. Official		External Driver Configuration						
gt of taid Port.			External Davise Cardynation	(Granited Section)	10. [fs. H. M.]				
Pightped10									
Rental Internation			Section and Advance for your constants.						
	4								
	41								
	41								
			Contract Contract						
	tartig follows		Check names are setting a	AB 101					
					Contraction of the local division of the loc				
	Pageala				2				
	Progress				20				
	41								

K

- Expand Ethernet Device (General) in the Module List.
- Drag and drop **SLMP Connection** into the grey area. This is the MELSEC Communication Protocol.
- Select protocol "TCP" and choose a Port No. between 1025-4999 or 5010-65534.
- Save the setting by pressing **Close with Reflecting the Setting** at the top.

	R ProgRo	Ethen	ernet Confi	puration (Built-in Etherne puration Edit View Close	e with Discarding th	e Setting: Ck	ove with Reflecting	the Setting				_ ×	election 4
A Monitor Configuration Program Program Program Provide Configuration A Label Device Device Continent Configuration Configuration			No. No.	Hodel Name Hodel Name Hodel States SUMP Connection Hodel	Communication Method	Protocal	Fixed Buffer Send Rooky Setting	P. Address 192.156.3.250 192.156.3.250	C Port No. 1025	Sensor/Devce PAC Address	tos. am	Medica Edit	Target:
€° Input Response €° Analog Input F Analog Output €° Expansion Boerc Eliterisory Cast Rea Module Information Remote Research	Progress	Outpu		ILINP Cha National C			_				,	Costlend A Superconstrain Module A Superconstraint Module (Specification) John when specify open method by SUMP v	

Apply the new project setting.

90 A F	Setting Service	Set in the	195				7 -d PCN/y	
Normal Configuration Property Configuration Propert	Transfer Lander States		12 Overlande Haller 12 Overlande Haller 13 Overlande Haller 14 Overlande 14 Overlande 15 Overla				Ref. (A) (A) (A) Capitr Target RC. (A)	A Det
	ter cer find head Peoples		Check Station the Solution	tu -		arry .		

Now all that's left is to write these settings to the PLC.

K-7

K



• In the top menu, press **Online** > **Write to PLC**.

MELSOFT Gill Works3 (Untitled Project)					- 0 ×
Project Mit Find Replace Convert	View Drites Debug Dispectics Tool W	Andre Hidy			
IN CONTRACTOR	. Current Connection Distinution	10000000000000000000000000000000000000	1 1 1 1 1 0 0 P Ver. 11100		
NADITORTHY	P And hern P.C.				
transfer 1.5	Write to PLC				The second se
18-1910 A	Verify with PLC.				T-d PCN/
	Remote Operation(5) -				SV 6. (10) 12-14
ET Medale Configuration	Safety FLC Operation.				
🖬 📰 Peyers	Redundant PLC Operation(0)				THE DAY (THE
e nimer	CHI Metory Operation.				Ospier Target: Al H
a Caller	Dates PLC Date.				
B Device Comment	User Data				
II Down Mensory	Set Ocok				
Device Initial Value	Marchae				
Contract Presenter	TE Payer's Malagement (Dolos).				
Ex REACTU	Watch				
#* CHUFmenster	Use Subsetuation				
E E, Module Parameter		and the second			
ES Oberrar Pint					
 High Served V/O 					10, (s., it., M., Uk.)
1 logal Bequire Terrs					input the Configuration Col., 9 18
git Analog Input					process of the same second
C Analog Dripel					
B Mension Cond Parameters					
Molds Manualan					
Renots Factword					
and a second sec					
_					
2	log est.)				
Connection Decema. "ENavigation	Copy Pepe				
				in the second seco	

Expand Parameter, make sure "Module Parameter" is checked, and press Execute.

* O 4 H	and sources supe											First PCHy	12
had before the	China Data Operation								-		×		
	Dates Sering Rated Ps	PCRM										CELLA M (LAP)	
una:			. 121	diam'r.	. 12	A WILLIAM						Chapter Target:	1
	AND A COLOR	A REAL PROPERTY AND	1000	- Contract	and the second	Contraction of the local division of the loc							
Device Commune	Personation = Pelgram(F)	Select All	Lippend										
	Cook/Coss AR(7)	Decelor: All'NI	• 0584	at enterey		Peniny Cert	A Statupt/wdushada						
boke wila take anco	Pedule hank/Coto Hank				Censi -	160	Last Change	Sox (Ityte)			3		
	Section Process		0										
	G 😰 Parancier												
CPU Farmelei	Distantia	sneter/Ohi Farsneter	2				306/2030 5-23-41 PM	NetORIAN	ed in	_			
A Distance and	Studie Tax	nele:	•			-	306/2020 5-54-56 PM	Not Calculate	nd .	_			
enclisted Percent	B Herey Ca	(Relatedar)					\$06/0030 1 20 51 PM	NUCRUM	ed .	_		and the second se	100 1
P High Speed 1/0	ing Barrels Fas	ined.		_			3/36/3030 5-23-31 PM	Not Caludate	el			PC. 18. 18.	<u>[u.</u>]
1 Input Response Terre	Chabad Labert		0									input the Derivative	
al Analogingut	Color Jac		0	_	_	_	306/3030 5/22/41/94	Netcalcale	H.	_			
Analog Chipel	- Se Program		0			_							
Memory Cond Taxasire			- []		-	-	306(2)30 1(23)4144	NICKUM	N .	_			
And in Information	Device More	a.	0		-	1				2			
	Shallin Henner Gasach Warnary Gasachy	Pagan Renau	aras Gaada	Market Similary					-				
	Size Salivanter								0.07mg				
	lagerd	Sea Wenne											
	a test	Pager:	. Anto	mailer Iria		feature	de la breast						
	a transf	R Barrow Co. C.					1.1						
	Decase i	a white day							1000				
	440-351 yr 140	Angun-		natur atto		ayan kan	iana (annan						
								200		11.000	-		_



K-8

NOTE: TCP or UDP?

We support both the TCP and UDP protocols but recommend using TCP as this protocol is less error-prone.

Your PLC is now ready and you can continue setting up your StrideLinx router by selecting a communication protocol.

Select a communication protocol

First, select a communication protocol. This is the protocol that your StrideLinx router uses to communicate with the PLC.

• Go to **Devices** (1) in the main menu, select your StrideLinx router (2) open its **Services** tab (3), and press **Add service** (4).



• Name the PLC (1), enter the PLC's IP address (2), and press Next (3).

× Add service	
Device 1	
Please specify a target for this service.	
Name R	
IP address eg. 192.168.140.100	
	NEXT

• Select the **Data source** service type.



K-9

StrideLinx Appendix K: Set Up Data Source Using MELSEC protocol

• Select "MELSEC Communication Protocol" from the drop down list and enter the following details:

Data Source Settings					
Field	Description				
Port	Enter the Port No. that you configured in your PLC.				
	This is named "Host Station Port Number" in GX Works2.				
MELSEC Series	The Mitsubishi MELSEC PLC series to which your PLC belongs.				
	If you're unsure, please consult the Mitsubishi website. "QnUCPU" is Mitsubishi's notation for every MELSEC-Q Series PLC with CPU type Q.U.CPU, for example Q04UDVCPU or Q26UDEHCPU.				
Transport protocol	Select the same protocol that you configured in your PLC.				
Network No. and PC No.	If configured in the PLC, enter the correct settings here. If not, leave the default settings.				
	Applicable when using a custom MELSEC PLC network.				
Request destination module I/O No. and Request destination module	If configured in the PLC, enter the correct settings here. If not, leave the default settings.				
station No.	Applicable when using a specific I/O module for communication.				
Authentication Type	The Ethernet connection in the PLC may be password protected. Enter the password or leave it empty if no password is configured on the PLC.				

• Press **Add** to create the data source.

Add variables (new, import)

Once you've added a Data Source and selected a communication protocol, you can start adding variables. This is done in the configurator tool, specifically designed to quickly **add**, **duplicate**, **import**, **export**, and **remove** variables.

- Go to **Devices** in the main menu, select your StrideLinx router, open its **Services** tab, and edit the PLC's services.
- Select **Data source** and press **Open configurator**.
- To add a variable press Add variable.

You can choose to:

- Manually add new variables
- **Import** variables from a file (or device)

Manually add new variables

- Press Add new variable.
- Enter your variable's **name**, **type**, additional information, and press Add]. The table below contains explanatory text for each text field. Use GX Works to find these values for each variable that you want to log.

	Data Tag Input Fields	
Field	Description	Example
Name	Enter a name for the variables.	Temperature
Туре	The variable's data type	Unsigned word
Device Type	The variable's device type	D - Data register
Device No.	Address in the PLC memory	100
Factor (optional)	Multiplies the value (leave empty if boolean)	0.1
Unit (optional)	Displayed text behind the value	Celsuis

You can easily duplicate 🗅 this variable if you're adding variables that are only slightly different. This way you only have to make small adjustments.



NOTE: After this next step, the config push, the device will temporarily disconnect to reconfigure its network settings and will automatically reconnect. This may take a minute.

Press Push changes in the config tab to complete the setup.



K-11

Κ

Import variables from a file (or device)

You can easily **copy variables from one device to another** by exporting the variables and then importing them in your new device.

When you press Import from CSV-file, you'll see a browse window.

- Select a CSV file to import and press **Open**.
- When the file has been read, press Add to add all variables to your data source.



NOTE: After this next step, the config push, the device will temporarily disconnect to reconfigure its network settings and will automatically reconnect. This may take a minute.

• Finally, press **Push changes** in the config tab to complete the setup.



Now that you've added the variables, you can test if they're configured properly.

Test variables

The test utility is used to **check if all the added variables are set correctly**. It shows the **status** of every variable and displays the variables' **latest values** if everything is configured correctly. If not, it will show an error message.

In the configurator, press **Run test**.



A connection will now be set up to stream the data directly to your computer, using:

- Port: 443
- Transport Protocol: TCP
- Application Protocol: WebSocket

Unexpected result?

If the test utility shows unexpected values, please check if the addresses and data types of all variables are entered correctly.

If you get no data at all, please also check that the above listed port and protocols are not being blocked by your computer's or company's firewall.

Connecting StrideLinx to Q series Ethernet module QJ71E71-100 with MELSEC Protocol

← Edit service		
Lo Chris ADC Router2		
Protocol* a MELSEC Communication Protocol	Port* b	
CPU* C Q (other CPU types)	Transport protocol*	•
Network No.* e	PC No.* 1 FF	
Request destination module I/O No.* 9 03FF	Request destination module station No.	
Authentication type * None		*
	o variables	
REMOVE	CANCEL	CONFIRM

- a. Choose the MELSEC Communication Protocol
- b. The port number needs to match the "Host station Port No." field in the "Open settings" dialog described later in this document. NOTE: the value configured in StrideLinx platform is in decimal format but the value in the Mitsubishi programming software is in Hex format. So in the example above, using a value of 2050 here should be 0802 in the Mitsubishi programming software.
- c. Choose the "Q (other CPU types)" option.
- d. Choose TCP transport protocol.
- e. Use a value of 0 for the "Network Number".
- f. Leave the default value of FF for the "PC number".
- g. Leave the default value of 03FF for the "Request destination module I/O No".
- h. Use a value of 0 for the "Request destination module station No".



Module setup in the Mitsubishi programming software:

• Double click on the "Network param" option on the left-hand side tree under the "Parameter" section of the project. This will generate a new dialog box.



• Select the "MELSECNET/Ethernet" option in the "Network parameter" dialog.

	Module 1	
Network type	Ethernet 🗸	1
Starting I/O No.	0000	1
Network No.		
Total stations		Τ
Group No.	(Ţ
Station No.		Π
Mode	On line 👻	
	Operational settings	
	Initial settings	L
	Open settings	
	Router relay parameter	
	Station No.<->IP information	
	FTP Parameters	
	E-mail settings	
	Interrupt settings	Г

• Configure the settings as shown in the dialog above.

K-15

Strid Linx Appendix K: Set Up Data Source Using MELSEC protocol

• Next, click on the "Operational settings" button to open a new dialog.

Communication data code Ginary code Ci ASCII code	Initial timing Do not wait for OPEN (Communications impossible at STOP time) Always wait for OPEN (Communication possible at STOP time)			
IP address Input format DEC. IP address 10	11 0 156	Send frame setting © Ethernet(V2.0) © IEEE802.3		
I Enable Write at RUN time ■ Enable Write at RUN time	e TCP Existe © Use th © Use th	nce confirmation setting— ie KeepAlive ie Ping		
	End Cancel			

- Configure the options as shown above.
- IP address: choose a unique IP address that is compatible with the subnet of the LAN side of your StrideLinx router.
- Click on the "End" button after setting up this dialog.

	Protocol	Open system	Fixed buffer	Fixed buffer communication procedure	Pairing open	Existence confirmation	Host station Port No.	Transmission turget device IP address	Transmission target device Port No.
1	TCP 🔻	Unpassive	🕶 Receive 👻	Procedure exist 👻	Disable 👻	No confirm 👻	0802		
Z			•					-tooline	
3	-			-	-	-			
4	-	1 2		-	-	-			
5	-	-			-	-			
6	-			-	-	-			
7	-				-	-			
8	-			-	-	-			
9	-			-	-	-			
10	-			-	-	-			
11	-			-	-	-			
12	•			-	-	-			
13	•			-	-	-			
14	-			-	-	-			
15	-			-	-	-			
16	-		• 1 · · · ·	-		·	5 S.		
				Enc	1	Cancel			

• Now click on the "Open settings" button in the "MELSECNET/Ethernet" dialog to display the settings above.

- Configure your ethernet module to match the settings above. NOTE: the "Host station Port No." must match the setup in the StrideLinx router. The value shown here is in hex format while the value in the StrideLinx router is in decimal format.
- Click on the "End" button and write these values to your PLC. A power cycle may be required on the PLC for these settings to take effect.